

INTRODUCTION TO VERSION 5.2.1 December 2004

TABLE OF CONTENTS

Registration and Title System Version 5.2.1 Remote Sticker Printing System December 2004

ı	 RSPS EQUIPMENT RSPS Equipment	- 7 7
II	 CONFIGURATION OF LAPTOP BY COUNTY ADMINISTRATOR Initial Setup and Reboot Flash Drive Update and Reboot County Administrator Setup of County Security for Subcontractor Supervisor 	- 8 - 12
III	 RECONFIGURATION OF LAPTOP BY COUNTY ADMINISTRAT Post Implementation	
IV	 CONFIGURATION OF LAPTOP BY SUBCONTRACTOR SUPER To Log On To Windows	- 20 - 21 - 22 25 - 26 - 28 30 31 - 32 - 33 34 - 35
V	REMOTE STICKER PRINTING BY SUBCONTRACTOR Renewal – Subcontractor————————————————————————————————————	- 43 - 44 - 45 - 47 - 50 - 51 - 53 - 54
VI	 SUBCONTRACTOR RENEWAL EVENT AT COUNTY Subcontractor Renewal Disk Entry – Subcontractor Supplied Diskette Subcontractor Renewal Diskette Report (RTS.POS.2012) 	- 59


	 Subcontractor Renewal Report – Final (RTS.POS.2011)- Receipt/Sticker Form	66 67
	To Review, Delete or Modify Renewal Entries in the	O1
		68
	Delete EntryModify Entry	
	 Error Messages 	
	 To Leave The Subcontractor Renewal Event Before All 	
	·	73
	 To Leave The Subcontractor Renewal Event Before All Renewals In The Bundle Are Entered 	74
	Manual Entry – Keyboard/Scanner	75
		82 83
	 To Review, Delete or Modify Renewal Entries in the 	84
	Delete Subcontractor Renewal	
	 Modify Subcontractor Renewal 	85
VII	RSPS STATUS UPDATES	87
VIII		91
	Inventory Detail Report (RTS.POS.5161)	
	■ Transaction Reconciliation Report (RTS.POS.5231)	
	Inventory Summary Report (RTS.POS.5221)Batch Inventory Action Report (BIAR) (RTS.POS.9901)	
	 Substation Inventory Report (RTS.POS.9901) 	
	County-Wide Inventory Report (RTS.POS.5903)	
	Monthly Production Report (RTS.PRD.9482)	97
	Inventory Received Report (RTS.POS.3021)	98
ΙX	VERSION 5.2.1 ACTIVITY CHANGES	99


RSPS EQUIPMENT

Ensure that all devices are properly assembled and connected before powering on the RSPS laptop.

RSPS LAPTOP







SCANNER



DONGLE (Adapter)



USB FLASH DRIVE



WIRELESS LAN ADAPTER



WIRELESS PRINT SERVER FRONT



BACK



2300 PRINTER



RSPS EQUIPMENT SETUP

Wireless Printing

NOTE: A power strip with at least four plugs is required.

- 1. Connect printer cable and power cord to Printer
- 2. Connect Printer to power source
- 3. Connect printer cable to Wireless Print Server (LPT1 port)
- 4. Connect Wireless Print Server to power source (a row of green lights will appear)
- 5. Power up Printer
- 6. Insert Wireless LAN Adapter into Laptop PC Card slot
- 7. Connect Scanner serial connection (female) to Dongle serial connection (male)
- 8. Connect Dongle USB connection to rear USB connector on Laptop
- 9. Connect Scanner to power source
- 10. Connect Laptop to power source
- 11. Power up Laptop (black button, white dot)
 - Laptop will flash message that a connection has been made
 - Wireless LAN Adapter will reflect a solid green light (if no connection made, proceed to "No Connection Present" below

No Connection Present

- 12. If no connection made, shutdown Laptop and power off
- 13. Power off Wireless Print Server (hold key until off)
- 14. Power on Wireless Print Server (hold key until on)
- 15. Power up Laptop (black button, white dot)
 - Laptop will flash message that a connection has been made
 - · Wireless LAN Adapter will reflect a solid green light
- 16. If still no connection, repeat steps 12 15

Local Printing

- 1. Connect USB cable and power cord to Printer
- 2. Connect Printer to power source
- 3. Connect printer USB cable to Laptop USB connector
- 4. Connect Scanner serial connection (female) to Dongle serial connection (male)
- 5. Connect Dongle USB connection to rear USB connector on Laptop
- 6. Connect Scanner to power source
- 7. Connect Laptop to power source
- 8. Power up Printer
- 9. Power up Laptop (black button, white dot)

CONFIGURATION OF LAPTOP BY COUNTY ADMINISTRATOR [INITIAL CONFIGURATION]

The County Administrator must configure each new (never configured) RSPS laptop prior to issuance to subcontractor. There are four user groups associated with the Remote Sticker Printing System (RSPS):

- Administrator County administrator
- Supervisor Subcontractor supervisor/manager
- Power User Subcontractor experienced personnel
- User Subcontractor or new personnel

The chart below displays events allowed for use by each Subcontractor and DTA user group.

		Administrator	Supervisor	Power User	User
DTA	Print Sticker	~	~	~	~
	Reprint Sticker	~	~	✓	×
	Void Sticker	~	>	~	×
	Reports	~	~	✓	✓ No Date Range
	Reprint Reports	~	*	~	×
	Recovery	~	~	×	×
	Printer Setup	~	~	×	×
Subcontractor	Renewal	~	~	~	~
	Reprint Sticker	~	~	~	×
	Void Sticker	~	~	~	×
	Reports	~	~	✓	✓ No Date Range
	Reprint Reports	~	~	~	×
	Export	~	~	✓	×
	Printer Setup	~	~	×	×
Administration	Login/Logout	~	~	✓	~
	Setup	~	×	×	×
	User Administration	~	~	×	×

Initial Setup and Reboot for RSPS

The County Administrator must complete the following steps to configure each new laptop for operation:


STEP	ACTION
1	Ensure that the dongle (adapter) and scanner are plugged into the RSPS laptop ports.
	NOTE: The dongle (adapter) that arrives with a laptop MUST remain with <u>that</u> laptop.
2	Power on the RSPS laptop the Log On to Windows screen appears.

LOG ON TO WINDOWS SCREEN




STEP	ACTION
3	Input the VTR supplied:
	User Name
	Password
4	Select "OK" the Windows XP Desktop appears.

WINDOWS XP DESKTOP



5 Select "Start" or press Ctrl + Esc a **Menu List** appears.

MENU LIST



STEP	ACTION
6	Select "Start RSPS" the Login – COM001 screen appears.

LOGIN SCREEN



STEP	ACTION	
7	Select the "I Accept" radio button.	
8	Input the VTR supplied:	
	User ID	
	Password	
9	Select ENTER the Setup (COM003) screen appears.	

SETUP SCREEN




The Setup screen will appear <u>blank</u> during the initial (first time) configuration.



Completed Setup screen using the following steps:


STEP	ACTION
10	Select the following:
10	County Information: Select a 3-digit Office Issuance Number with
	County Name.
	Drop-down list displaying county numbers and names
	Laptop will restart if changed
	• County No - This field will auto populate after a 3-digit Office
	Issuance Number selection is made from the drop-down list.
	County Name – This field will auto populate after a county selection
	is made from the drop-down list.
11	RSPS Type:
	Select the Subcontractor radio button.
	When Subcontractor is selected, the RSPS Information reverts
	to subcontractor information after log in by employee. Laptop
	will restart if changed.
	· · · · · · · · · · · · · · · · · · ·
	allow the Subcontractor to issue plates.
	• Max Export Days - This field defaults to 7-days, the maximum
	allowed before export of transactions from the Subcontractor to the
	county. Enabled only for a subcontractor.
	Max Export Trans – This field defaults to 300 transactions, the
	maximum allowed to be held by a Subcontractor before export to the
	· · · · · · · · · · · · · · · · · · ·
12	county. Enabled only for a subcontractor.
12	Input the following: RSPS Information:
	Subcontractor ID – Enter the Subcontractor ID number from the current
	RTS system (maximum 3 characters). Laptop will restart if changed.
	Name - Enter the Subcontractor name from the current RTS system
	(maximum 30 characters).
	RSPS ID – Enter a unique identifier for the RSPS system.
	Format is S111Y.
	• "S111" is auto populated based on the entry in the
	Subcontractor ID field. User must enter "Y"
	 Naming conventions are as follows:
	S = Subcontractor
	111 = Subcontractor ID
	Y = sequential from A through Z (for multiple RSPS)
	systems at the same location)
	Address – enter the subcontractors address from the current RTS
	system
	 Address fields 1 and 2 maximum 30 characters
	 City field maximum 19 characters
	 State field must be 2 characters
	 ZIP field must be 5 numeric characters
	 'ZIP + 4' field must be 4 numeric characters
13	Select ENTER the Confirm Action (CTL001) screen appears.
	(

CONFIRM ACTION SCREEN



STEP	ACTION
14	Select "Yes" the System Shutdown Message screen appears.

SYSTEM SHUTDOWN MESSAGE




STEP	ACTION
15	Select "Exit" or wait 10 seconds. The RSPS laptop restarts and the Log
	On to Windows screen appears.

Flash Drive Update and Reboot


At this point, the RSPS laptop is set to the appropriate subcontractor location. The laptop must be updated with new programming (if any) and subcontractor supervisor information. The Universal Serial Bus (USB) Flash Drive is a portable file stick used to load the RTS application from the RTS desktop and plugs into the laptop.

LOG ON TO WINDOWS SCREEN





RSPS UPDATE PROCESS SCREEN



STEP	ACTION
20	Select "OK," the system restarts (various screens will flash on and off)
	and the Log On to Windows screen appears. (Process 1 – 2 minutes)
21	Remove the USB Flash Drive from the RSPS laptop after the
	system restarts.


County Administrator Setup of County Security for Subcontractor Supervisor

LOG ON TO WINDOWS SCREEN




STEP	ACTION
22	Input the VTR supplied:
	User Name
	Password
23	Select "OK" the Windows XP Desktop appears.

WINDOWS XP DESKTOP



STEP	ACTION
24	Select "Start" or press Ctrl + Esc a Menu List appears.

MENU LIST




STEP	ACTION
25	Select "Start RSPS" the Login – COM001 screen appears.


LOGIN SCREEN



STEP	ACTION
26	Select the "I Accept" radio button.
27	Input the VTR supplied:
	User ID
	Password
28	Select "Enter" the RSPS screen (desktop) appears.




STEP	ACTION
29	Select "User Admin" the User Administration (COM004) screen appears.




STEP ACTION 30 Select the "Add" button the User Properties (COM005) screen appears.

USER PROPERTIES SCREEN



Enter the following information:




STEP	ACTION
37	If additional supervisors are to be added, select the "Add" key repeating steps 30 through 36 to add county administrator(s) and/or additional subcontractor supervisor(s)
38	Select "Cancel" for the RSPS screen (desktop) to reappear.

RSPS SCREEN



STEP	ACTION
39	Press Ctrl + Esc a Menu List appears.

MENU LIST



STEP	ACTION
40	Select "Shut Down" the Shut Down Windows screen appears.

SHUT DOWN WINDOWS SCREEN



STEP	ACTION
41	Use the up and down arrow keys to select "Shut down" and select "OK."
	The system shuts down and the RSPS laptop powers off.
42	The RSPS laptop is now ready to be issued to the subcontractor.

RECONFIGURATION OF LAPTOP BY A COUNTY ADMINISTRATOR (POST-IMPLEMENTATION)

The configuration of a subcontractor RSPS laptop can be changed from one subcontractor to another. The configuration can also be changed from subcontractor RSPS laptop or vice versa. Only a County Administrator, with access to Setup, can make such a change. When the change is made, all database information for the prior configuration is deleted.

IMPORTANT***Ensure that all existing information (renewal transactions, reports, etc.) have been accounted for <u>before</u> reconfiguring the RSPS laptop.

To reconfigure an RSPS laptop, the following steps must be completed:

1. Ensure that the dongle (adapter) and scanner are plugged into the RSPS laptop.

NOTE: The dongle (adapter) that comes with a laptop MUST remain with that laptop.

- 2. Power on the RSPS laptop, the **Log On to Windows** screen appears.
- 3. From this point, refer to Steps 1–15 and 22–42 beginning on page 8.

CONFIGURATION OF LAPTOP BY SUBCONTRACTOR SUPERVISOR

To Log On to Windows

- A user must log on to Windows in order to start RSPS
- Windows will automatically lock after two hours of inactivity
- Once locked, only the user previously logged on or an administrator can unlock

To log on to Windows and start RSPS, the following steps must be performed:


STEP	ACTION
1	Ensure that <u>all devices</u> (dongle [adapter] and scanner, printer or wireless
	print server, etc.) are properly assembled and connected before powering
	on the RSPS laptop
2	Power on the RSPS laptop The Log On to Windows screen appears.

LOG ON TO WINDOWS SCREEN



STEP	ACTION
3	Input the VTR supplied:
	User Name
	Password
4	Select "OK" the Login – COM001 screen appears

LOGIN SCREEN



STEP	ACTION
5	The user is now logged on to Windows and RSPS is started.

To Login to RSPS

- A user must login to use RSPS
- RSPS will lock up for one minute after three unsuccessful login attempts
- A user will remain logged in indefinitely as long as transactions are being performed
- RSPS will force another login after 10-minutes of inactivity


To login to RSPS, the following steps must be completed:

STEP	ACTION
1	The Login – COM001 screen appears.

LOGIN SCREEN



STEP	ACTION			
2	Select the "I Accept" radio button.			
3	Input the following:			
	User ID			
	Password			
4	Select "Enter" the RSPS screen (desktop) appears.			



STEP	ACTION
5	Only those events allowed under the user's configuration are available. Note above that Setup is grayed out for the supervisor.
6	 The "Export Status" box displays: Number of renewal transactions completed since the last export and maximum number of renewal transactions allowed Current day of the current export cycle and maximum number of days allowed in the current export cycle (number of days between required exports)

To Add A New Employee


A subcontractor supervisor may add, delete, and modify employees and additionally may reset passwords for employees. There are four user groups associated with the Remote Sticker Printing System (RSPS):

- Administrator County administrator
- Supervisor Subcontractor supervisor/manager
- Power User Subcontractor experienced personnel
- User Subcontractor new personnel

NOTE: Refer to the placement chart on page 8, showing the Subcontractor and DTA events allowed for use by each user group.


To add a new employee, the subcontractor supervisor must complete the following steps:

STEP	ACTION
1	Login to RSPS The RSPS screen (desktop) appears.




STEP ACTION 2 Select "User Admin" the User Administration (COM004) screen appears.

USER ADMINISTRATION SCREEN




STEP	ACTION
3	Select "Add" the User Properties (COM005) screen appears.

USER PROPERTIES SCREEN




STEP	ACTION					
4	User ID – Enter a unique identification number for the user (7 – 8 characters)					
5	First Name – Enter first name of user. Required (maximum 15 characters)					
6	MI – Enter middle initial of user, not required					
7	Last Name – Enter last name of user, required (maximum 15 characters)					
8	Select User Group – Select Supervisor, Power User or User					
9	Select the "Add" button to add a user ID for a subcontractor Supervisor, Power User or User and the User Administration (COM004) screen reappears displaying the user name as entered.					
	User Administration COM004 User ID User Name User Group KTHOMAS KIP THOMAS Supervisor					
	SWEGNER STAN WEGNER User Add Modify Delete Cancel					
	NOTE: The first time an employee logs on to the RSPS, he and/or she will use " PASSWORD " as the password. The system will prompt the employee to enter their own password choice. Refer to the "Password Change" section for additional information.					
10	If additional entries are to be made, select the "Add" key repeating steps 4 through 9 to add an additional "Supervisor," "Power User" and/or "User."					
11	Select "Cancel" for the RSPS screen (desktop) to reappear. NOTE: The RSPS screen (desktop) displays enabled icons only for those events allowed under the user's configuration.					



To Delete An Employee

To delete an employee, the subcontractor supervisor must complete the following steps:

STEP	ACTION
1	Login to RSPS the RSPS screen (desktop) appears.




STEP	ACTION
2	Select "User Admin" the User Administration (COM004) screen
	appears.

USER ADMINISTRATION SCREEN




STEP	ACTION
3	Select the User Name to be deleted. NOTE: A user currentloy logged onto the system cannot delete his/her personal User ID and User Name (another user must delete you from the system).
	NOTE: The "CNTYADMN" User ID cannot be deleted.
4	Select "Delete" the Confirm Action (CTL001) screen appears.

CONFIRM ACTION SCREEN



STEP ACTION 5 Select "Yes" the employee is deleted and the User Administration (COM004) screen appears.

USER ADMINISTRATION SCREEN




STEP	ACTION
6	Select "Cancel" the RSPS (desktop) screen appears.


To Modify Employee RSPS Access Rights

To modify an existing employee's RSPS attributes, the subcontractor supervisor must complete the following:





STEP	ACTION						
2	Select "User	Admin"	the	User	Administration	(COM004)	screen
	appears.						




STEP	ACTION
3	Select the employee whose attributes are to be modified.
4	Select "Modify" the User Properties (COM005) screen appears.

USER PROPERTIES SCREEN



STEP	ACTION
5	User ID – Enter a unique identification number for the user (7 – 8
	characters)
6	First Name – Enter first name of user. Required (maximum 15
	characters)
7	MI – Enter middle initial of user, not required
8	Last Name – Enter last name of user, required (maximum 15
	characters)
9	Select User Group – select "Supervisor," "Power User" or "User"
10	Select the "Modify" button to modify a user ID for a subcontractor
	Supervisor, Power User or User and the User Administration
	(COM004) screen appears.




STEP	ACTION
11	If additional entries are to be made, select the "Modify" key repeating
	steps 4 through 10 to modify Supervisor, Power User(s) and/or User(s).
12	Select "Cancel" the RSPS screen (desktop) appears.


To Reset Password

When necessary, a password can be reset to the word "Password" by an Administrator (county) or supervisor (subcontractor). To reset the password, the following steps must be completed:

STEP	ACTION
1	Login to RSPS the RSPS screen (desktop) appears.




STEF	ACTION
2	Select "User Admin" the User Administration (COM004) screen
	appears.




	STEP	ACTION
Ī	3	Select the employee whose password is to be reset.
	4	Select "Modify" the User Properties (COM005) screen appears.

USER PROPERTIES SCREEN



STEP	ACTION
5	Press the Alt + "R" keys to select Reset Password a check "√" appears in
	the check box.
6	Select "Modify" the password is "reset" to the word "Password" and the
	User Administration (COM004) screen appears.



STEP	ACTION
7	Select "Cancel" for the RSPS screen (desktop) to reappear.

To Change Password

A password may be changed at any time. To change a password, the following steps must be completed:

STEP ACTION 1 Power on the RSPS laptop and the Login (COM001) screen appears.

LOGIN SCREEN



STEP	ACTION
2	Select the "I Accept" radio button.
3	Enter the following:
	User ID
	Password
4	Press Alt + "N" to place a check "\" in the check box beside New
	Password.
5	Select ENTER the Password Change (COM002) screen appears.

PASSWORD CHANGE SCREEN




STEP	ACTION
6	Enter a New Password
	It must be different from the previous five passwords
	It must be have a minimum of 6 or maximum of 8 characters.
7	Press the TAB key to move to the Check Password Field.
8	Re-enter the new password to confirm the change.
9	Select the ENTER key to update the password. The RSPS screen
	(desktop) appears.

To Change Print Destination

When necessary, RSPS can be configured allowing stickers to print on a new or different printer. This should only be required in instances such as printer breakdowns, movement of the RSPS system or printers within a location, or the addition of printers to a location. To change printer destination, the following steps must be completed:


STEP ACTION 1 Login to RSPS the RSPS screen (desktop) appears.



STEP ACTION


2 Select "Printer Setup" the **Printer Setup** (COM006) screen appears.

PRINTER SETUP SCREEN



Appears if "**Local Printing**" <u>is</u> selected Printer connected to RSPS via cable

Wireless Printing



Appears if "**Local Printing**" is <u>not</u> selected Printer connected to RSPS via wireless print server

 All printers that have been configured in the RSPS configuration file are displayed

Current printer selection is highlighted

STEP	ACTION
3	Select a new printer using the UP/DOWN arrow keys to toggle to another selection.
4	Select ENTER the print destination is updated and the RSPS screen (desktop) appears.

To Stop RSPS

RSPS may be stopped from any screen within the application

All completed transactions are saved

To stop RSPS, the following steps must be completed:




STEP	ACTION
1	Press Ctrl + Esc a Menu List appears.

MENU LIST



STEP	ACTION
2	Select "Stop RSPS" the Windows XP Desktop appears.

WINDOWS XP DESKTOP




To Start RSPS [if already logged on to Windows]

To start RSPS, the following steps must be completed:


STEP	ACTION
1	Press Ctrl + Esc a Menu List appears.

MENU LIST



STEP	ACTION
2	Select "Start RSPS" the Login – COM001 screen appears.

LOGIN SCREEN



To Start System Shutdown


The system (Windows, RSPS application, laptop, and all devices) may be shut down from any point (screen)

All completed transactions are saved

To shut down the system, the following steps must be completed:

STEP	ACTION
1	Press Ctrl + Esc. A menu list appears.





STEP	ACTION
2	Select "Shut Down" the Shut Down Windows screen appears.

SHUT DOWN WINDOWS SCREEN



STEP	ACTION
3	Use the up and down arrow keys to select "Shut down" and select OK.
	The system shuts down and the RSPS laptop powers off.

To Start RSPS System Update

RSPS laptops must be updated with new programming, virus protection, etc.


Updates are completed using a USB Flash Drive provided by the county

Updates must be completed at least once a month

The RSPS laptop must be at the **Log On to Windows** screen to initiate the update (must be logged off RSPS and Windows)

To complete the RSPS system update, the following steps must be completed:

STEP	ACTION
1	If necessary, log off by pressing Ctrl + Esc a Menu List appears.



STEP	ACTION
2	Select "Shut Down" The Shut Down Windows screen appears.


SHUT DOWN WINDOWS SCREEN



3 Use the up and down arrow keys to select "Log off rspsuser" and select "OK." The Log On to Windows screen appears.

LOG ON TO WINDOWS SCREEN





RSPS UPDATE PROCESS SCREEN



STEP	ACTION
7	Select "OK" the system restarts (various screens will flash on and off) and
	the Log On to Windows screen appears. Approximately 1 – 2 minutes

LOG ON TO WINDOWS SCREEN



STEP	ACTION
8	Remove the USB Flash Drive from the RSPS laptop <u>after</u> the system
	restarts.
9	The RSPS Version Number will change only if system programming was updated (if only virus definitions were updated, the RSPS Version number will not change).
10	The RSPS laptop is now ready for use.

TO FIX USB DONGLE

If the configuration file of the dongle (adapter) is corrupted in the Windows registry, the scanner will not function. In such cases, the Fix USB Dongle event may be used to repair the configuration file and to restore the scanner to operating condition.

To run the Fix USB Dongle event, the following steps must be completed:


STEP	ACTION
1	Ensure that the dongle (adapter) is plugged into the RSPS laptop.
	NOTE: The dongle (adapter) that comes with a laptop MUST remain with
	that laptop.
2	Power on the RSPS laptop and the Log On to Windows screen appears.

LOG ON TO WINDOWS SCREEN




STEP	ACTION
3	Input the following:
	the User Name
	for the Password
4	Select "OK" the Windows XP Desktop appears.

WINDOWS XP DESKTOP




STEP	ACTION
5	Select "Start" or press Ctrl + Esc the Menu List appears.

MENU LIST



STEP	ACTION
6	Select "fix usb dongle.reg" the Registry Editor screen appears.

REGISTRY EDITOR SCREEN



STEP	ACTION
7	Select "Yes" the Windows registry is updated and the Registry Editor
	screen reappears with a new message.

REGISTRY EDITOR SCREEN



STEP	ACTION
8	Select "OK" the Windows XP Desktop appears.
9	Restart the RSPS laptop and verify that the scanner is operational.

REMOTE STICKER PRINTING BY SUBCONTRACTOR

Renewal - Subcontractor

A Subcontractor must verify the following information concerning the vehicle record before processing a registration renewal using RSPS.

- Vehicle owner must be a resident of the subcontractor county
- Registration renewal notice must reflect the subcontractor county
- Vehicle registration must be current and within the 90-day renewal window
- Subcontractors serving multiple counties must have an RSPS laptop for each county
- When a renewal notice barcode is scanned, the RSPS laptop checks all transactions in its database (including transactions, less than 60 days old, that have already been exported) to verify that that renewal has not already been processed. If a match is found, an error message is presented

To process a vehicle registration renewal, the following steps must be completed:


STEP	ACTION
1	Login to "RSPS" the RSPS screen (desktop) appears.

RSPS SCREEN



STEP	ACTION
2	Select "Renewal" the Renewal (SUB001) screen appears with no visible
	information. The statement "Scan a renewal notice or press "Cancel" to return." appears at the top.

RENEWAL SCREEN [Before Scan]



STEP ACTION 3 Scan the barcode on the vehicle Registration Renewal Notice. The Renewal (SUB001) screen reappears, displaying vehicle information read from the scan of the barcode.


RENEWAL SCREEN [After Scan]



STEP	ACTION
4	The vehicle information displays as follows:
	Doc No – Document number from the RTS system
	Sticker Type – Item code and description of the sticker to be issued
	Plate Type – Item code and description of the current plate
	• Issue Date – Date on which the sticker is issued (defaults to current
	date)
	VIN – Vehicle Identification Number (The VIN is not required when
	processing a no VIN trailer.)
	Year – Expiration year of the sticker to be issued (defaults to the year)
	following the year of the issue date)
	Curr Plt – Current plate number
	Exp Mo/Yr – Expiration month and year prior to renewal
	Fee – Registration renewal fee

STEP	ACTION
5	Select the following (if applicable):
	Issue New Plate –
	 Select only if new plates are being issued as part of the renewal
	 Enabled only if subcontractor has been authorized by the county to issue new plates
	When selected, a check "√" appears in the box and the input field is enabled
	 Enter the new plate number (if applicable)
6	Select "ENTER," the Sticker/Receipt Form will print and the Renewal (SUB001) screen reappears, with no visible information, the "Export Status" TRANS indicator increases by one, and the sticker/receipt prints.
7	Select "Cancel" the RSPS screen (desktop) appears and the Main Menu appears.
8	Attach Customer Copy of the vehicle Registration Renewal Notice to the Sticker/Receipt form and give to the customer.
9	Retain County Copy of the vehicle Registration Renewal Notice for presentation to the county.

Sticker/Receipt Form



- Receipt is on top 2/3 of form; sticker is on bottom 1/3 of form
- Sticker information includes plate number, last 8 digits of VIN (except when
 processing no VIN trailers), county name, expiration month and year, and
 barcode (barcode not printed on plate sticker)
- System prints applicable sticker; "Void" is printed on the other sticker
- Subcontractor name and address print on receipt

Reprint Sticker - Subcontractor

The sticker may be reprinted until the transaction has been exported or voided.

Reprints must be completed on the same laptop as the original transaction.

A reprint does not change the TRANS number in the Export Status box

STEP	ACTION
1	Login to "RSPS" the RSPS screen (desktop) appears.

RSPS SCREEN



STEP	ACTION
2	Select "Reprint Sticker" the Reprint Sticker (SUB002) screen appears.

REPRINT STICKER SCREEN



STEP	ACTION
3	This screen displays all non-voided stickers printed since the last export to diskette and includes the following information:
	Plate No – Current plate number associated with the renewal transaction
	VIN – Vehicle Identification Number associated with the renewal transaction
	Date/Time – Date and time the renewal transaction was processed
	Processed by – User id of the employee who processed the renewal transaction
4	Selection may be made by scanning or highlighting the selected line item.
	Two selection options are available as follows:
	Scan the Registration Renewal Notice barcode corresponding to the sticker to be reprinted.
	 If found, the renewal transaction appears is highlighted.
	♦ If not found, error message appears.
	Scroll through the displayed transactions until the correct transaction is highlighted.
5	Select "Reprint," the sticker/receipt prints, and the RSPS screen
	(desktop) appears.
	NOTE: The "Export Status" TRANS indicator <u>does</u> <u>not</u> change.
6	Attach the Customer Copy of the vehicle Registration Renewal Notice to
	the Sticker/Receipt and give to the customer.
7	Retain the County Copy of the vehicle Registration Renewal Notice and
	all prior sticker/receipt's print for presentation to the county.

Void Sticker - Subcontractor


A sticker and associated renewal transaction may be voided any time <u>prior to export to diskette</u>.

The void must be completed on the same laptop as the original transaction.

To void a sticker, the following steps must be completed:

STEP	ACTION
1	Login to "RSPS" the RSPS screen (desktop) appears.


RSPS SCREEN



STEP ACTION

2 Select "Void Sticker" the **Void Transaction** (SUB003) screen appears.

VOID TRANSACTION SCREEN



STEP ACTION

- This screen displays all non-voided sticker printed since the last export to diskette and includes the following information:
 - Plate No Current plate number associated with the renewal transaction
 - VIN Vehicle Identification Number associated with the renewal transaction
 - Date/Time Date and time the renewal transaction was processed
 - Processed by User ID of the employee who processed the renewal transaction

STEP	ACTION
4	Select the renewal transaction to be voided. Two selection options are available as follows:
	 Scan the Registration Renewal Notice barcode corresponding to the sticker to be voided If found, the renewal transaction is highlighted. If not found, an error message appears. Scroll through the displayed transactions until the correct transaction
5	is highlighted. Select "Void" and the Void Confirmation (SUB004) screen appears.
	Void Confirmation SUB004 Are you sure you want to void the selected transaction? Yes No
	 Select "Yes," the transaction is voided, and the RSPS screen (desktop) appears. NOTE: The "Export Status" TRANS indicator does not change.
	Retain all voided sticker/receipts (original and reprints) for presentation to the county.


Subcontractor Balancing Report

- The Subcontractor Balancing Report (RSPS.0001) is used to reconcile processed transactions against funds received.
- It lists all transactions processed since the prior report or for a specified date/time range.
- It is sorted by time.

To print the Subcontractor Balancing Report, the following steps must be completed:


STEP	ACTION
1	Login to "RSPS" the RSPS screen (desktop) appears.

RSPS SCREEN



STEP	ACTION
2	Select "Reports" the Select Report Range (SUB005) screen appears.
3	Used to reconcile processed transactions against funds received
	 Lists all transactions processed since the prior report or for a specified date/time range

SELECT REPORT RANGE SCREEN





The following report options are available: Since Last Run to Present • All transactions processed since the last report Date/Time Range • All transactions processed during the specified date/time range • "From" date must be within 60 days prior to the current date • "From" date/time must be before the "To" date/time • "To" date/time must be prior to the current date/time • Not available for "User" configuration

STEP	ACTION						
5	The following input fields are available:						
	"From" Date – Start date for the date/time range, enabled if "Date/Time Range" is selected, and defaults to the current date.						
	"To" Date – End date for the date/time range, enabled if "Date/Time Range" is selected, and defaults to the current date.						
	"From" Time - Start time for the date/time range, enabled if "Date/Time Range" is selected, and defaults to "00:00:00."						
	• "To" Time – End time for the date/time range is enabled if "Date/Time Range" is selected and defaults to the current time.						
6	Select the report to be printed.						
7	Select "ENTER" the report prints, refer to the Reports section to see format.						
8	Should be printed on regular paper manually fed through Tray 1 of the printer						
9	When print is completed, the RSPS screen (desktop) appears						

Subcontractor Balancing Report (RSPS.0001)

SUBCONTRACTOR BALANCING REPORT KIP'S KARS RSPS.0001 TARRANT

SUBCONTRACTOR ID : 001
REQUESTED BY : KTHOMAS
RSPS ID : 5001A
REPORT TYPE : SINCE LAST REPORT
TRANSACTIONS FROM : 08/04/2004 13:39:49 THROUGH 08/04/2004 13:48:30

DATE	TIME	USER ID	PLATE NUMBER	PREV PLATE NUMBER	VIN	EXP MO/YR	STKR CODE	PLT CODE	PROCESSED	REPRINTED	VOIDED	FEES
08/04/2004	13:42:11	KTHOMAS	YGC35D		1FALP6531WK114042	08/05	WS	PSP	1			62.80
08/04/2004	13:42:18	KTHOMAS	YGL81R		1MELM6538WK601949	08/05	WS	PSP	1			62.80
08/04/2004	13:42:31	KTHOMAS	955YDA	YGN85B	YV1LS5537W1413344	08/05	WS	PSP	1			62.80
08/04/2004	13:42:40	KTHOMAS	YGL66C		2FMDA5147WBB04081	08/05	WS	PSP	1			62.80
08/04/2004	13:42:51	KTHOMAS	123ABC	YGB56X	2FMDA5146WBA51017	08/05	WS	PSP	1			62.80
08/04/2004	13:43:35	CMUNOZ1	123ABC	YGB56X	2FMDA5146WBA51017	08/05	WS	PSP				
08/04/2004	13:43:44	CMUNOZ1	YGC35D		1FALP6531WK114042	08/05	WS	PSP		1		
08/04/2004	13:43:54	CMUNOZ1	YGL66C		2FMDA5147WBB04081	08/05	WS	PSP			1	-62.80
08/04/2004	13:44:15	CMUNOZ1	YGK89X		1G3WS52K6WF304813	08/05	WS	PSP	1			62.80
08/04/2004	13:44:31	CMUNOZ1	555DDD	YGL14S	1MELM6534WK600104	08/05	WS	PSP	1			62.80
08/04/2004	13:44:39	CMUNOZ1	YGL71C		2FMDA5145WBB09120	08/05	WS	PSP	1			62.80
08/04/2004	13:45:22	SWEGNER	XYM52J		2FMDA51UXWBB33929	08/05	WS	PSP	1			62.80
08/04/2004	13:45:27	SWEGNER	ҮНН89М		3FALP6531WM106595	08/05	WS	PSP	1			62.80
08/04/2004	13:45:42	SWEGNER	999BBB	YHH91M	3FALP1135WR111164	08/05	WS	PSP	1			62.80
08/04/2004	13:45:54	SWEGNER	YGL76F		3FALP1136WR129561	08/05	WS	PSP	1			62.80
08/04/2004	13:46:13	KTHOMAS	XYM52J		2FMDA51UXWBB33929	08/05	WS	PSP		1		
08/04/2004	13:46:22	KTHOMAS	YHH89M		3FALP6531WM106595	08/05	WS	PSP			1	-62.80
08/04/2004	13:46:38	KTHOMAS	555DDD	YGL14S	1MELM6534WK600104	08/05	WS	PSP			1	-62.80
08/04/2004	13:47:03	KTHOMAS	YGL14S		1MELM6534WK600104	08/05	WS	PSP	1			62.80
08/04/2004	13:47:46	KTHOMAS	YHH89M		3FALP6531WM106595	08/05	WS	PSP	1			62.80
							TOTA	LS	14	3	3	690.80

. . . END OF REPORT . . .

RUNDATE 08/04/2004

RUNTIME 13:48:30 PAGE 1

Export - Subcontractor


- Export parameters are established during RSPS configuration.
- Once the established parameters are met, additional renewal transactions may not be processed until an export has been performed (other functions remain available)
- Defaults to a maximum of 300 transactions and 7 days.
- Export time periods run from midnight to midnight
- The "Export Status" box on the RSPS screen (desktop) may be viewed to determine the number of renewal transactions or days remaining until an export is required

NOTE: An export must be performed at least once every seven days. If no renewals have been processed during a 7-day period, an Export Report will print reflecting no transactions. This report must be submitted to the county.

To export transactions to a diskette, the following steps must be completed:


	STEP	ACTION
Ī	1	Place regular paper into tray 1 of the printer.
Ī	2	Login to "RSPS" the RSPS screen (desktop) appears.

RSPS SCREEN




STEP	ACTION
3	Select "Export" the Export Transactions (SUB006) screen appears.

EXPORT TRANSACTIONS SCREEN



STEP	ACTION
4	The following information is displayed:
	• Export Date/Time – Date and time when a particular set of transactions was exported to a diskette
	Disk Sequence No – Sequence number assigned to a diskette when a particular set of transactions was exported
5	Select "Export New" the Insert Diskette (SUB007) screen appears.

INSERT DISKETTE SCREEN



STEP	ACTION						
6	Insert the diskette, select "Enter" and the RSPS screen (desktop) appears.						
7	The following functions are performed:						
	 All transactions processed since the previous export are exported to the diskette and the transactions are marked as "exported." 						
	The diskette is marked with an identifying Disk Sequence Number						
	The Subcontractor Export Report (RSPS.002) prints, as seen below.						
	The "Export Status" TRANS and DAY indicators are reset.						
8	The Subcontractor Export Report should be printed on regular paper manually fed through Tray 1 of the printer. Refer to the Reports section to view this report.						
	NOTE: On the Subcontractor Export Report, new plates issued by the subcontractor are shown in the "PLATE NUMBER" column.						

STEP	ACTION				
9	Present the following documentation to the county tax office:				
	Diskette				
	Subcontractor Export Report				
	 Corresponding county copies of Vehicle Registration Renewal Notice 				
	Reprint/Void documentation				
	Funds				

Subcontractor Export Report (RSPS.0002)

RSPS.0002					SUBCONTRACTOR E KIP'S K TARRAN	ARS	EPORT					
DISK SEQUE	BY : : NCE NO :	KTHOMAS S001A 1	13:39:49	THROUGH	08/04/2004 15:45:01							
DATE	TIME	USER ID	PLATE	PREV PLATE	VIN	EXP MO/VR			PROCESSED	REPRINTED	VOIDED	FEES
8/04/2004 8/04/2004	13:42:18 13:42:31		YGL81R 955YDA	YGN85B	1FALP6531WK114042 1MELM6538WK601949 YV1LS5537W1413344 2FMDA5147WBB04081	08/05 08/05	WS WS	PSP PSP PSP	1 1 1			62.80 62.80 62.80 62.80
8/04/2004 8/04/2004	13:42:51 13:43:35	KTHOMAS	123ABC 123ABC	YGB56X YGB56X	2FMDA5146WBA51017 2FMDA5146WBA51017 1FALP6531WK114042	08/05 08/05	WS WS	PSP PSP PSP		1		62.80
8/04/2004 8/04/2004	13:43:54 13:44:15	CMUNOZ1 CMUNOZ1	YGL66C YGK89X		2FMDA5147WBB04081 1G3WS52K6WF304813 1MELM6534WK600104	08/05 08/05	WS WS	PSP PSP PSP	1		1	-62.80 62.80 62.80
3/04/2004	13:44:39		YGL71C		2FMDA5145WBB09120 2FMDA51UXWBB33929 3FALP6531WM106595	08/05 08/05	WS WS	PSP PSP PSP	1 1			62.80 62.80 62.80
8/04/2004 8/04/2004	13:45:42 13:45:54	SWEGNER SWEGNER	999BBB YGL76F	YHH91M	3FALP1135WR111164 3FALP1136WR129561 2FMDA51UXWBB33929	08/05 08/05	WS WS	PSP PSP PSP	1	1		62.80 62.80
8/04/2004	13:46:38	KTHOMAS	YGL14S	YGL14S	3FALP6531WM106595 1MELM6534WK600104 1MELM6534WK600104 3FALP6531WM106595	08/05 08/05	WS WS	PSP PSP PSP			1	-62.80 -62.80 62.80 62.80
						,		==		3		
RUNDATE 0 RUNTIME 1											:	PAGE 1

Re-Export - Subcontractor

Previous exports may be re-exported when necessary.

Previous exports are retained for 60-days from the date of original export.

To re-export transactions to a diskette, the following steps must be completed:

STEP	ACTION
1	Place regular paper into tray 1 of the printer.
2	Login to "RSPS" the RSPS screen (desktop) appears.

RSPS SCREEN




STEP	ACTION
3	Select "Export" the Export Transactions (SUB006) screen appears.

EXPORT TRANSACTIONS SCREEN



STEP	ACTION							
4	The following information is displayed:							
	 Export Date/Time – Date and time when a particular set of transactions was exported to a diskette Disk Sequence No - Sequence number assigned to a diskette when a particular set of transactions was exported 							
5	Select the export to be re-exported							
6	Select "Re-export Selected" the Insert Diskette (SUB007) screen appears.							

INSERT DISKETTE SCREEN



STEP	ACTION						
7	Select "ENTER" the RSPS screen (desktop) appears.						
8	The following functions are performed:						
	All previous data on the diskette will be erased						
	All transactions within the selected export are re-exported to the diskette						
	The Subcontractor Export Report prints						
	The "Export Status" TRANS and DAY indicators do not change						
	The Subcontractor Export Report (RSPS.0002) prints						
9	Present the following documentation to the county tax office:						
	Diskette						
	Subcontractor Export Report						
	Corresponding county copies of Vehicle Registration Renewal Notices						
	Reprint/Void documentation						
	Funds						

Reprint Reports - Subcontractor


Previous Subcontractor Balancing Reports and Subcontractor Export Reports may be reprinted, if necessary.

Previous reports are retained for 60 days from the date of the original report.

To reprint a report, the following steps must be completed:


STEP	ACTION
1	Place regular paper into tray 1 of the printer.
2	Login to "RSPS" the RSPS screen (desktop) appears.

RSPS SCREEN



STEP ACTION 3 Select "Reprint Reports" the Reprint Reports (COM007) screen appears displaying all reports with a date 60-days or less.

REPRINT REPORTS SCREEN



Before and After Selecting Report



STEP	ACTION					
4	The following information is displayed:					
	Report Date – Date on which a particular report was generated					
	Report Name – Name of a particular report					
	Report Preview – Preview of the selected report					
5	Select "Print" and the selected report reprints.					
6	Select "Cancel" the RSPS screen (desktop) appears.					

SUBCONTRACTOR RENEWAL EVENT AT COUNTY

Subcontractor Renewal

The **Subcontractor Renewal** event enables the county office to process registration renewals issued by a subcontractor. The following is a list of features for this event:

- Allows the county to process bar-coded renewal notices using keyboard/scanner entry
- Allows the county to process bar-coded inventory items using keyboard/scanner entry
- Allows the county to process subcontractor renewal transactions produced in the Remote Sticker Printing System (RSPS).
- All transactions are assigned transaction numbers and will appear on the close out unless a bundle is set aside.

Additional features include:

- Subcontractor Renewal event enhanced to allow diskette entry of renewals
 - Subcontractors will be issued an RSPS laptop to print stickers
- New RSPS Status Updates event added to facilitate RSPS laptop updates
 - Updates will be accomplished through use of a USB Flash Drive

The subcontractor will submit the following to the county tax office:

- Diskette containing renewal transactions (maximum 300 per diskette)
- Subcontractor Export Report
- County copies of Registration Renewal Notices
- Funds
- Reprinted and/or voided sticker/receipts

In most cases, subcontractor renewal transactions will be processed via diskette entry. However, if necessary, subcontractor renewals may still be input using keyboard or scanner entry. The county user can view subcontractor renewal line items on the screen and transactions from this event are recorded on the mainframe.

NOTE: The Subcontractor Renewal event is available while the system is in **Data Server Unavailable** mode.

Accessing from Main Menu

To access Subcontractor Renewal:


STEP	ACTION
1	Select Customer from the Main Menu by pressing the ALT + "C" keys.
2	Select Registration Only by pressing the "R." key.
3	Select Subcontractor Renewal by pressing the "S." key.


Disk Entry - Subcontractor Supplied Diskette

STEP	ACTION					
1	The Entry Preferences (REG050) screen appears giving an entry					
	choice of Subcontractor Supplied Diskette or Keyboard/Scanner.					


ENTRY PREFERENCES








SUBCONTRACTOR ENTRY





Subcontractor Renewal Diskette Report (RTS.POS.2012)

The Subcontractor Renewal Diskette Report (RTS.POS.2012) automatically prints information from diskette.

RTS.POS.2012 SUBCONTRACTOR RENEWAL DISKETTE REPORT WILLIAMSON WILLIAMSON COUNTY MAIN OFFICE

WORKSTATION ID

: 0 : KTHOMAS : 001 EDUCATOR'S CREDIT UNION : 09/13/2004 11:24:45 : 09/14/2004 12:48:35 : 3 REQUESTED BY SUBCONTRACTOR ID PREVIOUS EXPORT

EXPORT DISK SEQUENCE NO RSPS ID : S001A

PLATE

PREV			
PLATE	EXP	STKR	PLT

ISSUE DATE	NUMBER	NUMBER	VIN	MO/YR	CODE	CODE	USER ID P	ROCESSED	REPRINTED VOIDED	FEES
09/14/2004	ABC123	3SWP04	1GCEC19R2TE230733	11/05	WS	TKP	CNTYADM	1		62.56
09/14/2004	4RXF63		3B7HC13Z6TG187366	11/05	WS		CNTYADM	1		63.00
09/14/2004	BDD810	4GWN12	1GTGC34R1YR229133	11/05	WS	TKP	CNTYADM	1		72.46
								=======		=======

3 0 0 TOTALS 198.02

. . . END OF REPORT . . .

RUNDATE 09/17/2004

PAGE 1 RUNTIME 10:56:31

STEP	ACTION
13	The Registration Subcontractor Renewal (REG007) screen appears.


REGISTRATION SUBCONTRACTOR RENEWAL



STEP	ACTION
14	After entering the subcontractor-supplied diskette, the system will
	automatically display Plate, Sticker, or Plate & Sticker issued for the
	last transaction on the disk.
15	The system will automatically display the appropriate Sticker Item Code
	– Description (US – Plate Sticker or WS-Windshield Sticker) for the last
16	transaction on the disk.
16	The system will automatically display the appropriate Year of sticker issued for the last transaction on the disk.
17	The system will default to the current date as the Issue Date. However,
	the date may be changed on the previous screen and shown on this
	screen.
18	The user is encouraged to pay particular attention to the Doc No. , VIN ,
	and Plate . These entries are used to verify registration and if <u>any one of</u>
	the three are incorrect the registration will not update but will appear on
	an Error Report.
19	The Doc No verifies the correct vehicle record in the system and
	appears only in the Modify function.
20	The VIN verifies the correct vehicle record in the system and appears
	only in the Modify function. (The VIN is not required when processing no
21	VIN trailers.)
22	The New Plate displays new plate of issue and appears in the List Box.
22	The Curr Plt (the plate number currently on the vehicle) displays in the List Box.
23	The Exp Mo (number of month of expiration) displays in the List Box.
24	The Reg Class (the number of the vehicle registration classification)
	appears only on the Modify screen.
25	The Fee (the total fee printed on the renewal receipt) displays in the List
	Box
26	The Print function is disabled during disk entry.
•	

STEP	ACTION
28 29	In the List Box the vehicle renewal information appears as follows: The Input column indicates the method of entry. A "Diskette" icon indicates "diskette entry" mode. The Print column is blank when processing a subcontractor supplied diskette. The Issue Date column supplies the date entered on the previous screen. The Year column indicates the new expiration year (after renewal). The PIt Cd column indicates the new plate type code if "Plate" or "Plate and Sticker" is selected. The New PIt No column indicates the new plate number if "Plate" or "Plate and Sticker" is selected. The Stkr Cd column indicates the sticker type if "Plate" or "Plate and Sticker" is selected. (Ex: WS, US etc) The Curr PIt No column indicates the license plate number (after renewal). The Exp column indicates the registration month and year of expiration (before renewal). The Fee column denotes the total fees paid. Press the ENTER key to continue. Once all renewals in the bundle are correct on the Registration Subcontractor Renewal (REG007) screen, press the ENTER key. The total fees for the bundle appear on the Confirm Action (CTL001) screen. If "Yes," press "Y" or ENTER to view the Subcontractor Renewal Report – Final (RTS.POS.2011). If "No," press "N" to return to the Registration Subcontractor Renewal (REG007) screen. NOTE: The screen states "Total is \$ XXXXXX."
	Yes <u>N</u> o
30	Transactions are processed at the rate of 1 per second.
	A disk with 300 transactions should take 5 minutes to process. The Normal Advance of the Control of the C
31	The View Report screen for the Subcontractor Renewal Report- Final (RTS.POS.2011) appears.

VIEW REPORT




STEP	ACTION
32	If the Subcontractor Renewal Report is more than one page:
	To view the Next Page, press the "N" letter key.
	To view the Previous Page, press the "V" letter key.
33	To print the Subcontractor Renewal Report , press the "P" letter key.
	Otherwise, press the ENTER key. The system returns to the Main
	Menu.

Subcontractor Renewal Report - Final (RTS.POS.2011)

```
RTS.POS.2011
                                                            SUBCONTRACTOR RENEWAL REPORT - FINAL
                                                                            WILLIAMSON
                                                               WILLIAMSON COUNTY MAIN OFFICE
WORKSTATION ID
REQUESTED BY
                          : KTHOMAS
                       : AlHUMAS
: 001 EDUCATOR'S CREDIT UNION
: 09/17/2004
SUBCONTRACTOR ID
INPUT
DISK SEQUENCE NO
                       : 3
: S001A
RSPS ID
                           PREV
               PLATE
                           PLATE
                                                                     EXP STKR PLT
MO/YR CODE CODE
ISSUE DATE NUMBER NUMBER
                                               VIN
                                                                                                           TRANSACTION ID
                                                                                                                                            FEES
09/17/2004 RG2346 3SWP04 1GCEC19R2TE230733 11/05 WS TKP 24600038245112243 62.56
09/17/2004 4RXF63 3B7HC13Z6TG187366 11/05 WS 24600038245112331 63.00
09/17/2004 RG2345 4GWN12 1GTGC34R1YR229133 11/05 WS TKP 24600038245112430 72.46
                                                                                                                                           72.46
                                                                                                                   PAYMENT AMT
                                                                                                                                         198.02
                                                                  . . . END OF REPORT . . .
RUNDATE 09/17/2004
RUNTIME 11:24:27
                                                                                                                                               PAGE 1
```

- The Issue Date shown on this report is the date entered on the REG006 or REG007 screen
- Transactions are listed in ascending order (the first renewal processed is listed first on the report)
- For Diskette entry, Transaction IDs are assigned by the system in ascending order (the first renewal processed is assigned the first Transaction ID).
- For Keyboard entry, Transaction IDs are assigned by the system as each renewal is added.

Receipt/Sticker Form




- Receipt is on top 2/3 of form; sticker is on bottom 1/3 of form
- Sticker information includes plate number, last 8 digits of VIN (except when processing no VIN trailers), county name, expiration month and year, and barcode (barcode not printed on plate sticker)
- System prints applicable sticker; "Void" is printed on the other sticker
- Subcontractor name and address print on receipt


To Review, Delete or Modify Renewal Entries in the List Box:


Review, Deletion or **Modification** to renewal entries <u>must</u> be completed before proceeding to the **Subcontractor Renewal Report - Final** (RTS.POS.2011)screen.

Delete Entry





Modify Entry






Error Messages









To Leave The Subcontractor Renewal Event Before All Modifications In The Bundle Are Completed:

STEP	ACTION
1	If you decide not to modify the record, press the ESC key.
	The Confirm Action (CTL001) screen appears.
	NOTE: The screen states "Are you sure that you do NOT want to
	modify the renewal record?"
	If "Yes," press "Y" or ENTER.
	If "No," press "N."
2	If you decide to modify the record:
_	If the cursor appears in the inventory Year field and the inventory year is
	incorrect:
	• Use the BACKSPACE key to erase the incorrect information, type
	the correct information, and press the TAB key.
3	If the Plate Item Code - Description, Sticker Item Code - Description,
	or Year (of expiration of the new inventory) is incorrect:
	If issuing a sticker only, press the Shift + TAB keys.
	 If issuing a plate and sticker, press the Shift + TAB keys, twice.
	 If issuing a plate only, press the Shift + TAB keys, twice.
	 Press the first letter of the correct plate type
	And/Or
	 Press the UP ARROW/DOWN ARROW key, until the correct
	plate type appears.
4	The Issue Date field is disabled.
5	If the Doc No (the document number) is incorrect:
	Use the BACKSPACE key to erase the incorrect information and
	type the correct information.
	Press the TAB key.
6	If the VIN (the vehicle identification number) is <u>incorrect</u> :
	Use the BACKSPACE key to erase the incorrect information and
	type the correct information.
	Press the TAB key.
7	If the New Plate No is incorrect:
	To correct the New Plate ,
	Use the BACKSPACE key to erase the incorrect information and
	type the correct information.
8	If the Curr PIt (the current plate number) is incorrect:
	To correct the Curr Plt
	Use the BACKSPACE key to erase the incorrect information and
	type the correct information.
	Press the TAB key.
9	If the Exp Mo, Reg Class and/or Fee is incorrect:
	Press the TAB key as many times as necessary to advance to a field
	with incorrect information.
	Use the BACKSPACE key to erase the incorrect information and
	type the correct information.
10	The Print function is disabled.

STEP	ACTION
11	Press the ENTER key. The Subcontractor Renewal screen reappears.
	To modify more entries, repeat steps 1-9 as needed.

To Leave The Subcontractor Renewal Event Before All Renewals In The Bundle Are Entered:





Manual Entry - Keyboard/Scanner

STEP	ACTION
1	The Entry Preferences (REG050) screen appears giving an entry
	choice of Subcontractor-Supplied Diskette or Keyboard/Scanner.


ENTRY PREFERENCES




STEP	ACTION
2	The system defaults to Subcontractor Supplied Diskette. Press the ALT
	+ "K" keys selecting Keyboard/Scanner to process renewals manually,
	press the ENTER key to continue.
3	The Subcontractor Entry (REG006) screen appears.

SUBCONTRACTOR ENTRY





SUBCONTRACTOR RENEWAL




	ACTION
5	The screen defaults to issue a Sticker . If applicable, press the ALT + "P" keys to change to Plate or press the ALT + "T" keys to change to Plate & Sticker.
6	The system defaults to Sticker Item Code - Description (WS-Windshield Sticker), Year (current renewal year) and the Issue Date entered on the previous screen. Select the appropriate plate item code and/or select the appropriate sticker item code: • If each of the above is <u>correct</u> , proceed to Step 9. • If the one or more of the above is <u>incorrect</u> , press the TAB key to the appropriate field, press the UP ARROW/DOWN ARROW keys, until the correct plate type appears. • Press the TAB key to continue.
7	If necessary, change the Year and press the TAB key.
8	If the Issue Date is incorrect (the date the renewal was issued by the subcontractor): • Press the TAB key. Type the correct date (MM/DD/YYYY). • Press the TAB key. NOTE: If you change the date within the same batch, you will receive a separate registration report for each date entered.
9	The user is encouraged to pay particular attention to the Doc No. , VIN , and Plate in steps 10-11-12. These entries are used to verify registration against the database record and if <u>any one of the three</u> are incorrect the registration will not update, appearing on an Error Report.
10	 The Doc No field is required to add a subcontractor renewal transaction to the List Box. It is a 17-digit field. Type the 17-digit document number in the Doc No field. Press the TAB key to continue. NOTE: If you scanned the renewal, the system will automatically enter this information.


STEP	ACTION
11	 The VIN field is required to add a subcontractor renewal transaction to the List Box. It is a 22-digit field. Type the vehicle identification number in the VIN field. Press the TAB key to continue.
	NOTE: If you scanned the renewal, the system will automatically enter this information. (The VIN is not required when processing a no VIN trailer.)
12	If applicable, type the number of the new plate in the New Plate field. Press the TAB key.
	NOTE: This field will only appear if issuing Plate or Plate and Sticker. • Inventory should be allocated to the subcontractor.
	NOTE: If you scanned the renewal, the system will automatically enter this information. • If issued inventory is not allocated to the subcontractor, the
	 Inventory - Item Number Not Found (INV029) screen appears. Contact the inventory manager before proceeding. Press the ALT + "V" keys if this item was voided inventory and needs to be reused. Press the ENTER key if the inventory is not voided and you want to
	use it.
13	Scan or enter by keyboard information from the renewal notice. Go to Step 14 if you do not have scanners installed. If you have a barcode scanner and want to scan the registration renewal notice: • Point the scanner gun at the bar code on the registration renewal notice and press the trigger for the laser light to read the barcode.
	NOTE: If clerk scans an out of county renewal notice, the system displays warning message: "Renewal Notice is not for this county" but does not stop processing.
	NOTE: When scanning, verify that the system captured the scanned Information before proceeding. Scanning faster than the system can process information will produce the message, "Missed One or More Scans. Please Check Your Work!" will appear. Confirm your last few entries, including inventory, to ensure all information was captured accurately.
	***If renewal is scanned, proceed to Step 18.
14	Type the plate number currently on the vehicle in the Curr Plt field. Press the TAB key.
	NOTE: If renewal is scanned, the system will automatically enter this information.
15	Type the number of the month of expiration in the Exp Mo field. Press the TAB key.
	NOTE: Scanned renewal will automatically enter this information.
16	Type the numerical registration class in the Reg Class field. Press the TAB key.

STEP	ACTION
17	Type the total fee in the Fee field. Press the TAB key.
	NOTE: If renewal is scanned, the system will automatically enter this information.
18	The print feature is enabled and defaults to " $$ " checked. Press the ALT + "R" keys to remove a check " $$ " in the checkbox beside Print for each entry <u>not</u> requiring a printed receipt.
19	After verifying the entered information, press the ALT + "A" keys to Add the registration information to the List Box. • If the fee is less than \$25 or more than \$100, the Confirm Action (CTL001) screen appears.
	NOTE: A Confirm Action (CTL001) screen appears and message states "Fee Amount is less than \$25.00. Is this correct?"
	Fee Amount is less than 25.00. Is this correct?
	Yes No
	If the fee amount is over \$100.00, a message appears stating "Fee Amount" is more than \$100.00. Is this correct?"
	Fee Amount is more than 100.00. Is this correct?
	 If "Yes," press the "Y" or ENTER key. The renewal information appears in the List Box. If "No," press the "N" keys.
20	 In the List Box the vehicle renewal information appears as follows: The Input column indicates the method of entry. A "Hand" icon indicates "keyboard/scanner" entry mode. The Print column indicates the print function was selected and that a sticker will be printed for that particular transaction. The Issue Date column supplies the date entered on the previous screen.
	 The Year column indicates the new expiration year (after renewal). The Plt Cd column indicates the new plate type code if "Plate" or

STEP	ACTION
OILI	"Plate and Sticker" is selected.
	The New Plt No column indicates the new plate number if "Plate" or "Plate and Sticker" is selected.
	The Stkr Cd column indicates the sticker type if "Plate" or "Plate and
	Sticker" is selected. (Ex: WS, US etc)
	The Curr Plt No column indicates the license plate number (after renewal).
	The Exp column indicates the registration month and year of expiration (before renewal).
	The Fee column denotes the total fees paid.
	Registration Subcontractor Renewal REG007
	Subcontractor Id: 111 KIPS KARS Add a renewal Plate Sticker Plate & Sticker Plate Item Code - Description Sticker Item Code - Description WS-WINDSHIELD STICKER VIN 10/01/2004 4952357345345 New Plate Curr Pit Exp Mo Reg Class Fee BBB399 9 25 61.80 Print Add
	Transaction Summary Transaction(s) Entered: 5 Input Print Issue Date Year Pit Cd New Pit No Stkr Cd Curr Pit No Exp Fee **** □ 10/01/2004 2005 WS BBF877 09/2004 51.80 *** □ 10/01/2004 2005 WS BBF23M 09/2004 61.80 *** □ 10/01/2004 2005 WS BFT34D 09/2004 61.80
	Draft Report Enter Cancel Help
21	Receipts for all transactions <u>displaying a print symbol</u> will print when entry is complete and the ENTER key is selected.
22	Press the ALT + "A" keys or the ENTER key to add a transaction to the List Box.
	NOTE: Once the transaction appears in the List Box the cursor returns to the doc no field.
23	"To review, delete or change renewal entries in the List Box," follow the corresponding instructions in this section.
24	For each renewal in the bundle, repeat the appropriate steps. • If forced to leave the Subcontractor Renewal event before all renewals in the bundle have been entered, see the instructions at the end of this section.
25	Once all renewals in the bundle have been entered, press the ENTER key.
	The total fees for the bundle appear on the Confirm Action
	(CTL001) screen.
	If "Yes," press "Y" or ENTER. """ """ """ """ """ """ """
	If "No," press "N."
	NOTE: The screen states "Total is \$ XXXXX."



View Report



STEP	ACTION
28	If the Subcontractor Renewal Report is more than one page:
	To view the Next Page, press the "N" letter key.
	To view the Previous Page, press the "V" letter key.
29	To print the Subcontractor Renewal Report – Final (RTS.POS.2011),
	press the "P" letter key. Otherwise , press the ENTER key. The system
	returns to the Main Menu .

Subcontractor Renewal Report - Final (RTS.POS.2011)


RTS.POS.2011 SUBCONTRACTOR RENEWAL REPORT - FINAL WILLIAMSON WILLIAMSON COUNTY MAIN OFFICE : 0 : KTHOMAS : 001 EDUCATOR'S CREDIT UNION : 09/24/2004 WORKSTATION ID REQUESTED BY SUBCONTRACTOR ID PREV EXP STKR PLT
VIN MO/YR CODE CODE TRANSACTION ID PLATE PLATE
ISSUE DATE NUMBER NUMBER FEES 09/15/2004 R27FGD 1G1LV1456FJ098765 1FABP0987TH123456 1XPRH7654DF567932 1G1LV1456FJ098765 09/05 24600038252102948 09/05 WS 09/05 WS 09/15/2004 F34DGH 09/15/2004 S01RTF 24600038252103019 24600038252103058 50.80 160.40 PAYMENT AMT

. . . END OF REPORT . . .

RUNDATE 09/24/2004 RUNTIME 10:31:26

PAGE 1


Receipt/Sticker Form



- Receipt is on top 2/3 of form; sticker is on bottom 1/3 of form
- Sticker information includes plate number, last 8 digits of VIN (except when processing no VIN trailers), county name, expiration month and year, and barcode (barcode not printed on plate sticker)
- System prints applicable sticker; "Void" is printed on the other sticker
- Subcontractor name and address print on receipt

To Review, Delete or Modify Renewal Entries in the List Box:

Review, deletion, or modification to renewal entries should be completed before proceeding to the **Subcontractor Renewal Report - Final** (RTS.POS.2011)screen.



STEP	ACTION
5	The Registration Subcontractor Renewal screen reappears. Repeat
	steps 1-3 as necessary.
6	To change a highlighted entry in the List Box, select Modify Entry by pressing the ALT + "M" keys.

Modify Subcontractor Renewal

The Modify Subcontractor Renewal (REG009) screen appears.




STEP	ACTION
1	If you decide <u>not</u> to modify the record, press the ESC key. • The Confirm Action (CTL001) screen appears.
	NOTE: The Confirm Action (CTL001) screen appears and the message states "Are you sure that you do NOT want to modify the renewal record?" If "Yes," press "Y" or ENTER. If "No," press "N."
2	 If you decide to modify the record: The cursor appears in the inventory Year field. If the inventory year is incorrect: Use the BACKSPACE key to erase the incorrect information and type the correct information. Press the TAB key.
3	 If the Plate Item Code – Description or Sticker Item Code – Description is incorrect: If issuing a sticker only, press the Shift + TAB keys. If issuing a plate and sticker, press the Shift + TAB keys, twice. If issuing a plate only, press the Shift + TAB keys, twice. Press the first letter of the correct plate type And/Or Press the UP ARROW/DOWN ARROW key, until the correct plate type appears.
4	If the Issue Date (the date the renewal was issued by subcontractor) is incorrect : • There is no need to erase type over the existing date using the correct date (MM/DD/YYYY). • Press the TAB key.

STEP	ACTION
5	If the Doc No (the document number) is incorrect:
	Use the BACKSPACE key to erase the incorrect information and
	type the correct information.
	Press the TAB key.
6	If the VIN (the vehicle identification number) is incorrect:
	Use the BACKSPACE key to erase the incorrect information and
	type the correct information.
	Press the TAB key.
7	If the New Plate is <u>incorrect</u> :
	To correct the New Plate
	Use the BACKSPACE key to erase the incorrect information and
	type the correct information.
	Press the TAB key.
8	If the Curr Plt No (the current plate number) is <u>incorrect</u> :
	To correct the Curr Plt No
	Use the BACKSPACE key to erase the incorrect information and
	type the correct information.
	Press the TAB key.
9	If the Exp Mo, Reg Class and/or Fee is incorrect:
	Press the TAB key as many times as necessary to advance to a field
	with incorrect information.
	Use the BACKSPACE key to erase the incorrect information and
40	type the correct information.
10	If the user failed to deselect the print function initially the modify function can be used to receive a printed receipt. On the Modify Subcontractor
	Renewal (REG009) screen press the ALT + "R" keys to place a check
	" $$ " in the checkbox next to print on the screen.
	The the checkbox flext to print on the screen.
	NOTE: A printer symbol appears in the Print column of the List Box
	signifying selection of the print function.
	NOTE: Receipts for all transactions displaying a print symbol will print
	when entry is complete and the ENTER key is pressed.
11	Press the ENTER key. The Subcontractor Renewal screen reappears.
	To modify more entries, repeat steps 1-11 as needed.

RSPS STATUS UPDATES


- The RSPS Status Updates event is used to update Remote Sticker Printing System (RSPS) laptops with new programming, virus protection, etc. extracted from an RTS workstation and to record the updates from RSPS laptops into the RTS database
- USB Flash Drives are used to complete the updates
- Once a USB Flash Drive has been used by a county for updates, it may only be used by that county


MAIN MENU





STEP	ACTION
1	Select Local Options by pressing the ALT + "L" keys.
2	Select RSPS Status Updates by pressing the "R" key.
3	The RSPS Update Status (RSP001) screen appears.

RSPS STATUS UPDATE










Reports


Modifications made to reports to accommodate Point of Sale Sticker Printing follow:




TRANSACTION RECONCILIATION REPORT (RTS.POS.5231)


RTS.POS.5231	ION REPORT							
				WILLIAMSON				
			WILLIAMSO	ON COUNTY MAI	N OFFICE			m numb
WORKSTATION ID :	0							longer
REQUESTED BY :	KTHOMAS							own for
CASH DRAWER :	0							ntable
REPORT TYPE :	FOR LAST CLOS	EOUT					stic	ckers
TRANSACTIONS FROM :	09/20/2004 09	:41:31 THROUG	GH 09/20/20	004 10:14:14			\neg	
				CASH			- 1	/
				CHANGE/			-	/
CUSTOMER NAME - TRAN	ISACTION	PAYMENT		CHECK	FEE/ITEM	ITEM ITEM	-	ITEM
TRANSACTION ID		TYPE	PAYMENT	CHANGE*	DESCRIPTION	YEAR NUMBER	1/	PRICE
							-1 <i> </i>	
SUBCONTRACTOR RENEWA							17.	
24600038248100949, W	ORKSTATION 0 B	Y KTHOMAS			AUTOMATION FEE (LARGE	CNTY)		1.00
					CHILD SAFETY FUND	1	\$	1.50
					CNTY ROAD BRIDGE ADD-0	ON FEE	\$	10.00
					REFLECTORIZATION FEE	//	\$	0.30
					REG FEE-DPS	/	\$	1.00
					WINDSHIELD STICKER	2005	\$	47.00
						CUSTOMER SUBTOT		
	CUSTOMER SET	Q TOTAL S	3/17 73			CUSTOMER SET 9 TOT.		3/17 73
CUSTOMER SET: 10 (09/2		CHECK \$				COSTOMER SET 9 TOT	лш. ү	347.73
SUBCONTRACTOR RENEWA		CHECK V	123.02					
24600038248101144, W		Y KTHOMAS			AUTOMATION FEE (LARGE	CNTY)	\$	1.00
2100000002101011111,		1 111101110			CHILD SAFETY FUND	0.117	\$	1.50
					CNTY ROAD BRIDGE ADD-C	ON FEE	ŝ	10.00
					REFLECTORIZATION FEE		\$	0.30
					REG FEE-DPS		ŝ	1.00
					WINDSHIELD STICKER	2005	\$	50.96
					WINDONIEDD OTTORER	2003		
						CUSTOMER SUBTOT.	AL: \$	64.76
SUBCONTRACTOR RENEWA	L TRANSACTION							
24600038248101233, W		Y KTHOMAS			AUTOMATION FEE (LARGE	CNTY)	\$	1.00
					CHILD SAFETY FUND		\$	1.50
					CNTY ROAD BRIDGE ADD-C	ON FEE	\$	10.00
					REFLECTORIZATION FEE		\$	0.30
					REG FEE-DPS		\$	1.00
					WINDSHIELD STICKER	2005	\$	50.96
						CUSTOMER SUBTOT	AL: \$	64.76
	CUSTOMER SET 1		129.52			CUSTOMER SET 10 TOT.		129.52
	PAYMENT REPOR					FEES REPORT TOTAL		
			E	IND OF REPORT				
RUNDATE 09/20/2004								
RUNTIME 10:14:47								PAGE 3

INVENTORY SUMMARY REPORT (RTS.POS.5221)




BATCH INVENTORY ACTION REPORT (BIAR) (RTS.POS.9901)






SUBSTATION INVENTORY REPORT (RTS.POS.5923)



COUNTY-WIDE INVENTORY REPORT (RTS.POS.5903)



MONTHLY PRODUCTION REPORT (RTS.PRD.9482)

RTS.PRD.948 PRD2	2						MENT OF T						
							PRODUCTI FOR July, CALDWE	2004	RT				
EMPL ID:		101001	01 0011m			222	D	222	DDD0001				moma.
July 01	ADDR 0	ADLCOL 1	CLSOUT	INVVD 0	NONTTL 0	PDC 0	RENEW 32	REPL 1	RPRSTK 0	TITLE 2	VEHINQ 0	VOID	TOTAL 37
01 02 06 07 08 09 12 13 14 15 16 19 20 21	0 0 0 0 0 0 0 0 0	0 0 0 0 0 0 0 0 0 0 0	1 2 1 1 1 1 1 0 1 1	0 0 0 0 3 0 2 0 0 0 0	2 1 0	1 1 0 1	23 32 31 16 17 19 13 13 12 24 12	2 0 0 2 1 2 1 0 0 0	0 0 0 0 0 0 0 0 0	4 4 0 6 2 4 7 1 2 9 1 8	0 0 0 0 0 0 0 0 0 0 0	0 0 0 0 3 0 2 0 0 0 0	34 40 32 32 23 30 22 16 14 36 16 28
TOT	2	2	14	5	6	8	271	10	2	56	12	5	393

No Changes to the following reports:

- Fees Report (RTS.POS.5241)
- Payment Report (RTS.POS.5213)
- Void Report (RTS.POS.9001)

INVENTORY RECEIVED REPORT (RTS.POS.3021)

RTS.POS.3021 INVENTORY RECEIVED REPORT HOOD

HOOD COUNTY MAIN OFFICE

WORKSTATION ID : 200
REQUESTED BY : KTHOMAS
INVOICE NO : S11101

ws

TRANSID : 11120038166101244

DESTINATION : HOOD COUNTY MAIN OFFICE in CENTRAL

INVOICED ITEM | RECEIVED ITEM

ITEM ITEM ITEM ITEM BEGIN END BEGIN END CODE DESCRIPTION YEAR QUANTITY NUMBER NUMBER QUANTITY NUMBER NUMBER NUMBER

ATVS TICKER 2005 10 00051R 00060R ITEM REJECTED BY SYSTEM: THIS ITEM CODE IS PRINTABLE.

WINDSHIELD STICKER 2005 10 7386249WF 7386258WF ITEM REJECTED BY SYSTEM: THIS ITEM CODE IS PRINTABLE.

TTS TOW TRUCK VALIDATION STKR 2005 10 1TF 10TF

ITEM REJECTED BY SYSTEM: THIS ITEM CODE IS PRINTABLE.

• When an invoice is received, the system verifies that no printable inventory items (WS, US, TTS, ATVS) are included

 Printable Item Codes and message "Item Rejected By System: This Code Is Printable" are listed along with other (non-printable) inventory items

. . . END OF REPORT . . .

Only non-printable items are added to inventory

RUNDATE 06/30/2004

RUNTIME 10:12:48

VERSION 5.2.1 ACTIVITY CHANGES

PRIMARY EVENT SELECTION	SECONDARY EVENT SELECTION	ACTIVITY DESCRIPTION	STATUS
CUSTOMER Registration Only	Texas Online Internet Registration Renewal	Problem: The word "Official" misspelled.	Fix completed: 6490
	County Processing (Vendor Payment Report)	Problem: Two copies are sent to every data server in IVTRS counties.	Fix completed: Now only one 7112
	Internet Renewal	Problem: Did not delete transactions from the "shopping cart" when another county name was selected before completion of sale.	Fix completed: 6698 - 6790
	Renewal (POS)	Problem: Stock inventory issued in the Registration Renewal event was listed as "UNKNOWN" on the Inventory Detail Report and on Part I on the BIAR Report.	Fix completed: Now the Inventory Detail Report displays "U-ITEM NUMBER NOT FOUND" and on Part A of the BIAR Report. 6871
CUSTOMER Title/Registration	Title Application (Corrected)	Problem: When a record displays TX in the country field, USA BOX is checked on the Owner Entry screen displaying Country/Zip. An Error Message "The Owner Name/Address Fields Must Be All Bank Or Mandatory Fields Must Be Completed" appears. The field must be completed before continuing.	Fix completed: The USA box will not be checked. If TX appears in the Country field, the address format will become international. 5914
	Correct Title Rejection	When a record displays TX in the country field, USA BOX is checked on the Owner Entry screen displaying Country/Zip. An Error Message "The Owner Name/Address Fields Must Be All Bank Or Mandatory Fields Must Be Completed" appears. The field must be completed before continuing.	Fix completed: The USA box will not be checked. If TX appears in the Country field, the address format will become international. 6188
		Problem: Change of Lienholder address from USA to non-USA does not display a change on the receipt (example "TX" to "GERM" displays "TX" on the receipt).	Fix completed: 6685

PRIMARY EVENT SELECTION	SECONDARY EVENT SELECTION	ACTIVITY DESCRIPTION	STATUS
Cont'd Title/Registration	COA	Problem: When there is more than one record with the same VIN, entry of the DocTypeCd from a previous record did not clear information when Record Not Applicable was selected.	Fix completed: 7246
INVENTORY	Receive Invoice	Problem: When receiving PLP inventory on a dummy invoice, the quantity is 1, the Begin and End fields are blank and ENTER is selected; the error message "For The Inventory Item Number, The Letter Or Number Combination Is Invalid" does not display.	Fix completed: 4608
	BIAR	Problem: Part F is split between two pages of the BIAR Report, one section at the bottom of page 1 (no inventory data) and the second on page 2 (inventory data).	Fix completed: All on one page 7128
	Batch Inventory Action Report	Problem: Part G heading is printing in place of Part H heading.	Fix completed: 6364
GLOBAL	Logon	Problem: When users press Enter before the Disclaimer screen shows, it is possible that the interface will not grasp the user name. The user name will be set to null and show no invalid user message.	Fix completed: Users should wait for the disclaimer panel before pressing enter, if a problem occurs an invalid user message appears. 7232